Accessing the Environment Monitoring System from Windows

Download and Install

https://support.apple.com/kb/DL999?locale=en_US

Or try

1.

Press the Windows key + "R" to open the "Run" dialog. Type "compmgmt.msc" without quotes in the Run dialog box, and press "OK" to open the Computer Management window.

2.

Click the arrow next to "Services and Applications" in the left pane to expand it, and then select "Services."

3.

Click the "Name" column header in the middle pane to sort the services alphabetically. Right-click "Bonjour Service" and choose "Start." Wait approximately five seconds for the service to start.

4.

Right-click "Bonjour Service" again, and select "Properties." On the General tab, choose "Automatic (Delayed Start)" from the drop-down list next to "Startup type" and click "OK." Close the Computer Management window.